## <u>Digital Photo Professional 出現錯誤信息「This program requires a display capable of 1024 x</u> <u>720...」時的處理方法</u>

當您的顯示屏的解像度大於 1024 x 720,但打開應用程式 < Digital Photo Professional > 時 卻出現如下圖錯誤信息「This program requires a display capable of 1024 x 720...」時,您可以按照以下步驟解決問題:



請根據所使用的 Windows 版本按以下連結:

Windows 10

Windows 8

Windows 7

如使用 Windows 10 系統,請參考以下步驟:

1. 在桌面空白位置,控滑鼠右鍵,然後選擇「(Display Setting)」

									1-					
								View Sort by	>					
								Refresh	-					
								Paste Paste shortcut						
							-	New	>					
							9	Display settings Personalize						
0			<i>p</i> -	015										14:51
Q	[[]]]	е		5.3						^ <b>%</b>	<b>(</b> )	ſ.	ENG	11/9/2015

## 2. 參考下圖將放大率調低

\*\*\*有關放大率設定,〔放大率〕乘 1024 x 720 的長寬數值不能大於螢幕解釋度,如 使用 1920 x 1080 的螢幕,當放大率 150% 乘 1024 x 720 長寬值為 1280 x 1080,因 此 1920 x 1080 的螢幕放大率可設定成 150%或以下。

← Settings			- 0 ×
🐯 SYSTEM		Find a setting	Q
Display	Customize your display		^
Notifications & actions			
Apps & features			
Multitasking	1		
Tablet mode			
Battery saver			
Power & sleep	Identify Datect		
Storage	Change the size of text, apps, and other items: 175%		
Offline maps	↓ <b>↓</b>		
Default appr	Orientation		
Default apps	Landscape $\checkmark$		
About			
	Apply Cancel		
= P 🗆	· 🐳 👩	^ 😵 📾 ላ)) ሰ	€ ENG 11/0/2015

3. 套用後,系統提示需要登出,建議按「Sign out now」登出後重新登入

Sign in again for	the best experience
Some apps will look their best	after you've signed out of Windows and signed in again.
	Sign out now Sign out later

4. 請重新開啟 < Digital Photo Professional >。

70	

如您使用 Windows 8 系統,請參考以下步驟:

1. 在桌面空白位置,控滑鼠右鍵,然後選擇「螢幕解析度(Screen Resolution)」



2. 按「改變文字和其化項目的大小(Make text and other items larger or smaller )」

		Screen Resc	olution		-	×
🔄 🏵 🗉 🕇 💆	Appearance an	d Personalization > Display > Screer	Resolution	✓ 🖒 Search (	Control Panel	Q,
	Change the a	appearance of your display				
				Detec	t fy	
	Display:	1. ThinkPad Display 1600x900 🗸				
	Resolution: Orientation:	1600 × 900 (Recommended) v Landscape v				
				Advanced s	settings	
	Project to a seco	nd screen (or press the Windows logo k	ey 🏭 + P)			
	Make text and ot	her items larger or smaller				
	What display set	tings should I choose?				
			ОК	Cancel Ap	ply	

3. 如按步驟 2 後出現以下畫面(如不是請到步驟 4),建議剔選「Let me choose one scaling level for all my displays」

		Display -		×
(	🕒 🌛 👻 🛧 🖳 🕨 Control Pane	el   Appearance and Personalization   Display   C  Search Control Panel		Q
	Control Panel Home	Change the size of all items		?
	Adjust resolution	Make text and other items on the desktop smaller and larger. To temporarily enlarge just part of the sci use the <u>Magnifier</u> tool.	reen,	
6	Calibrate color	Smaller Larger		
	Project to a second screen			
	Adjust Clear I ype text			
	1	Let me choose one scaling level for all my displays		
	L. L	Change only the text size		
		Instead of changing the size of everything on the desktop, change only the text size for a specific item.		
		Title bars v 11 v Bold		
	See also Personalization	A Some changes might not be applied until the next time you sign in to your PC.	ly	-
	Devices and Printers			

4. 参考下圖將放大率調低,然後按套用(Apply)

\*\*\*有關放大率設定,〔放大率〕乘 1024 x 720 的長寬數值不能大於螢幕解釋度,如 使用 1920 x 1080 的螢幕,當放大率 150% 乘 1024 x 720 長寬值為 1280 x 1080,因 此 1920 x 1080 的螢幕放大率可設定成 150%或以下。



5. 套用後,系統提示需要登出,建議按「立即登出 Log off now」,登出後重新登入

-完-

	Microsoft Windows	×
<b></b>	You must sign out of your computer to apply these changes Save any open files and close all programs before y sign out.	ou
	Sign out now Sign out late	r

6. 請重新開啟 < Digital Photo Professional >。

如使用 Windows 7 系統,請參考以下步驟:

1. 在桌面空白位置,控滑鼠右鍵,然後選擇「螢幕解析度(Screen Resolution)」



2. 按「改變文字和其化項目的大小(Make text and other items larger or smaller)」

	Dete <u>c</u> t Identify
Di <u>s</u> play: 1. SyncMaster 👻	
<u>R</u> esolution: 1280 × 1024 (recommended) $\checkmark$	
Orientation:	
Multiple displays: Extend these displays	
Ma <u>k</u> e this my main display	Advanced setting
Make text and other items larger or smaller	

3. 參考下圖將放大率調低,然後按套用(Apply)

\*\*\*有關放大率設定,〔放大率〕乘 1024 x 720 的長寬數值不能大於螢幕解釋度,如 使用 1920 x 1080 的螢幕,當放大率 150% 乘 1024 x 720 長寬值為 1280 x 1080,因 此 1920 x 1080 的螢幕放大率可設定成 150%或以下。



4. 套用後,系統提示需要登出,建議按「立即登出 Log off now」,登出後重新登入



5. 請重新開啟 < Digital Photo Professional >。