

LBP712Cx 在 Windows 透過 USB 連線連接印表機之驅動程式步驟 Driver installation procedure for LBP712Cx in Windows (Via USB)

****注意: 安裝驅動程式前請勿接駁 USB 線，以免系統發生錯誤****
**** Please don't plug the USB cable until the driver asked to do so****

下載及安裝步驟

Driver download and Installation procedure

1. 到佳能網站 <https://hk.canon/en/support/imageCLASS%20LBP712Cx/model>，下載印表機的驅動程式

Go to: <https://hk.canon/en/support/imageCLASS%20LBP712Cx/model>, download the printer driver

2. 選擇並下載以下檔案


Choose and download below files:

- 打印機驅動程式 / Printer Driver

[Windows x64bit] UFR II Printer Driver Vxx.xx


3. 下載的文件以自解壓縮檔檔案(.exe 格式)保存在指定的文件夾中，打開文件解壓縮。將在同一文件夾中創建新文件夾。新文件夾的名稱與解壓縮文件的名稱相同，進入新文件夾開啟「Setup.exe」開始安裝

Open the downloaded file, a same name new folder will be created. Go into new folder open "Setup.exe" start installation




4. 選擇「Yes」

Choose “Yes”




5. 選擇「USB Connection」，按「Next」


Choose “USB Connection”, press “Next”



6. 勾选「UFR II Printer Driver」，按「Next」
Select “UFR II Printer Driver”, press “Next”



7. 勾选「Canon LBP712C UFR II」，按「Next」
Select “Canon LBP712C UFR II”, press “Next”



8. Port 位置選擇「USBXXX」，按「Next」
Port select “USBXXX”, press “Next”

UFR II Printer Driver - Ver. 30.12

Printer Information

Set the port to be used for the selected printer.
Also, you can specify a name for the printer.

Selected Printer: Canon LBP712C UFR II
Use Driver: Canon UFR II Printer Driver Ver. 30.12
Port: USB006
Printer Name: Canon LBP712C UFR II

Set as Default
 Use as Shared Printer

Shared Name:

Devices: 1 (1 to 200) Current Printer: 1
Number of Printers to Set: 1

< Back Next > Cancel

9. 確認新增印表機資料，按「Start」
Confirm new printer information, press “Start”

UFR II Printer Driver - Ver. 30.12

The setup program will install the drivers with the following settings.
* Installation cannot be canceled once started.


Printer List for Driver Installation:

	Printer Name	Driver	Port
Add	Canon LBP712C UFR II	Canon LBP712C UFR II	USB006

< Back Start Cancel


10. 等待安裝程序完成

Waiting for the installation progress



11. 按「Restart」重啟電腦，完成安裝

Click "Restart" to restart computer, finish installation



-完-
-End-