

在 Windows 以 USB 方式安裝及連接 PIXMA TR160 打印機

Installing PIXMA TR160 on Windows via USB connection

****注意: 安裝驅動程式前請勿接駁 USB 線，以免系統發生錯誤****

**** Please don't plug the USB cable until the driver asked to do so****

以下步驟及畫面僅供參考，實際操作畫面可能因裝置型號、系統或軟件版本而有所不同。

The following steps and screens are for reference only, and the actual operation screens may vary depending on the device model, system, or software version.

下載及安裝步驟

Driver download and Installation procedure


1. 到以下佳能網站並下載印表機的驅動程式

Go to below Canon webpage and download the printer driver

<https://hk.canon/en/support/PIXMA%20TR160/model>

2. 選擇並下載以下檔案

Choose and download the file below




Master Setup (Windows)

<https://hk.canon/en/support/0101116303>


3. 按網頁內的〔Download〕按鈕，下載完成後開啟該檔案安裝

Click [Download] button in the webpage, and then execute the file after download was completed




4. 打開軟件後選擇語言，然後按〔OK〕

Choose the language after open the software, then click [OK]



5. 在居住地選擇〔亞洲〕，再按〔確定〕
Select [Asia] for place of residence, and then click [OK]



6. 在設定新印表機的視窗按〔開始設定〕
Click [Start Setup] on the windows of setting up new printer



7. 正在下載，請等候

Downloading, please wait



8. 按〔是〕同意許可協定

Click [Yes] to accept the license agreement




9. 可選擇是否同意傳送資訊至佳能，按〔同意〕或〔不同意〕

Click [Agree] or [Do not agree] for sending information to Canon Extended Survey Program



10. 請等候

Please wait



11. 確認印表機電源已開啟，再按〔下一步〕

Confirm power on the printer, then click [Next]



12. 請等候印表機偵測

Please wait for printer detection



13. 於連接方法選擇〔USB 連接(USB 電纜線)〕，再按〔下一步〕

Choose [USB Connection (USB Cable)] when choosing connection method, then click [Next]




14. 請等候印表機連接

Please wait for printer connection



15. 使用 USB 電纜線連接印表機和電腦

Connect the printer and the computer with USB cable




16. 請等候印表機偵測及軟件安裝

Please wait for the printer detection and software installation




17. 請等候安裝

Please wait for install



18. 安裝完成，按〔下一步〕

Installation complete, click [Next]



19. 安裝完成

Driver installation was completed



-完-

-End-